



MURA-572
Internal

IDENTIFICATION

Fortran Error Return, MU ERR1
704 FORTRAN Program
G. A. Westlund - May 2, 1960
Midwestern Universities Research Association, Madison, Wisconsin

PURPOSE

To provide evidence of error occurrence within a subroutine of the FORTRAN General Library.

RESTRICTIONS

ERR1 requires the use of the MURA 2, SHARE 1, or SHARE 2 printer boards (normally used with FORTRAN programs).

METHOD

Since FORTRAN, as originally supplied by IBM, contains no error returns in any of its subroutines, certain of these routines have been modified and added to the FORTRAN system to contain an exit to ERR1 for error indication. An example might be a square root routine, which exits if asked to take the square root of a negative number.

When entered, ERR1 prints one line:

ERROR RETURN FROM _ (NAME) _ _

where (NAME) is the 6 character name of the subroutine from which entered. In the example above, the name would be SQR5. After printing the line, ERR1 immediately returns (without stopping) to the subroutine.

USAGE

ERR1 is not available by means of FORTRAN statements. Any routine desiring to use it must have the following SAP code:

```
      α      TSX (ERR1),4  
      α+1    BCD 1(name)  
      α+2    return
```

STORAGE REQUIREMENT

59 Words

MUERR1	REM	0063 05010	ERR1	0001
	REM	MU ERR1 - FORTRAN ERROR RETURN	ERR1	0002
	REM	PRINTS ERROR SIGNAL ON 716 PRINTER	ERR1	0003
ERROR	SXD	ERROR+38,1	ERR1	0004
	SXD	ERROR+39,2	ERR1	0005
	SXD	ERROR+40,4	ERR1	0006
	STO	ERROR+41	ERR1	0007
	STQ	ERROR+42	ERR1	0008
	LDO	1,4	ERR1	0009
	LXA	ERROR+7,1	ERR1	0010
	PXD	6,0	ERR1	0011
	LGL	2	ERR1	0012
	PAX	12,2	ERR1	0013
	PXD	0,0	ERR1	0014
	LGL	4	ERR1	0015
	PAX	0,4	ERR1	0016
	CAL	ERROR+43	ERR1	0017
	TXH	ERROR+17,4,0	ERR1	0018
	TXH	ERROR+19,2,2	ERR1	0019
	TXH	ERROR+18,2,0	ERR1	0020
	ORS	ERROR+53,4	ERR1	0021
	ORS	ERROR+56,2	ERR1	0022
	ARS	1	ERR1	0023
	SLW	ERROR+43	ERR1	0024
	TIX	ERROR+7,1,1	ERR1	0025
	WPR		ERR1	0026
	LXA	ERROR+9,1	ERR1	0027
	CPY	ERROR+56,1	ERR1	0028
	CPY	ERROR+43	ERR1	0029
	CAL	ERROR+56,1	ERR1	0030
	ANA	ERROR+57	ERR1	0031
	SLW	ERROR+56,1	ERR1	0032
	TIX	ERROR+24,1,1	ERR1	0033
	CAL	ERROR+58	ERR1	0034
	SLW	ERROR+43	ERR1	0035
	LXD	ERROR+38,1	ERR1	0036
	LXD	ERROR+39,2	ERR1	0037
	LXD	ERROR+40,4	ERR1	0038
	CLA	ERROR+41	ERR1	0039
	LDO	ERROR+42	ERR1	0040
	TRA	2,4	ERR1	0041
	HTR	**	ERR1	0042
	HTR	**	ERR1	0043
	HTR	**	ERR1	0044
	HTR	**	ERR1	0045
	HTR	**	ERR1	0046
	HTR	32	ERR1	0047
	HTR	8704,4,26	ERR1	0048
	HTR	0	ERR1	0049
	HTR	0	ERR1	0050
	HTR	1280,0,4	ERR1	0051
	HTR	4096,2,32	ERR1	0052
	HTR	16512	ERR1	0053
	HTR	0,1	ERR1	0054
	HTR	0	ERR1	0055
	HTR	0	ERR1	0056
	HTR	16384,1	ERR1	0057
	HTR	19184,4,30	ERR1	0058
	HTR	1024,2,32	ERR1	0059
	HTR	**	ERR1	0060

HTR 32640763
HTR 32
END

ERR1 0061
ERR1 0062
ERR1 0063