

APPROVED BY

*J. Snyder*IDENTIFICATION

Variable Column, Variable Digit Rounded Fraction Print, MU PRF3

E. M. Zographos, February 28, 1957

Midwestern Universities Research Association, Madison, Wisconsin

PURPOSE

To print, on-line, one to five rounded fixed point fractions,  $F_i$ , in from one to five columns, with a five digit integer line label. The number of digits in each fraction is variable.

RESTRICTIONS

The MURA PRINTER BOARD 1 is required. See attached sheet for wiring diagram.

METHOD

Accuracy:  $\pm 5 \times 10^{-(P+1)}$ , where  $P$  = the number of digits

Range:  $-(1 - 2^{-35}) \leq F_i \leq 1 - 2^{-35}$

USAGE

Calling Sequence:

| UA SAP                |                    |
|-----------------------|--------------------|
| <u>Loc.</u>           | <u>Instruction</u> |
| $\alpha$              | TSX PRF3, 4        |
| $\alpha + 1$ (prefix) | B, P - 3, C        |
| $\alpha + 2$          | return             |

| MURASS       |                    |
|--------------|--------------------|
| <u>Loc.</u>  | <u>Instruction</u> |
| $\alpha$     | BTSX A 4           |
| $\alpha + 1$ | C N B P - 3 C      |
| $\alpha + 2$ | return             |

where:

(prefix) =  $N$  = the number of fractions,  $1 \leq N \leq 5$ .

B = integer label to identify line of print

C = location of first fraction, with successive fractions in  $C + 1$ ,  $C + 2$ , etc.

P = the number of digits,  $3 \leq P \leq 10$

On entry to this subroutine the fixed point fractions  $F_0, F_1, \dots, F_{N-1}$  in memory locations C,  $C + 1, \dots, C + N - 1$ , respectively, will be printed via the 716 printer as P digit rounded fractions. The fractions will appear in order,  $F_0, F_1, \dots, F_{N-1}$ , from left to right in N columns on one line.

Positive fractions are printed without sign, negative fractions with sign. The decimal point is not printed and is assumed to be immediately to the left of the first digit of the fraction. To the left of the N columns on the same line a five digit integer B will be printed to serve as a line label. At the far left of the line the letter F will appear to indicate that the numbers printed are fractions.

If the prefix is PZE, that is  $N = 0$ , and C is the location of any positive number, then just the label B is printed.

Space Required:

133 words program at:  
26 words temporary at:

UA SAP  
PRF3  
COMMON

| MURASS |
|--------|
| A      |
| T      |

#### CODING INFORMATION

Timing:  $511.6 + 3.8N$  ms. is the average time if the printer is not in motion upon entry. The printer will be kept running at full speed (150 lines/min.) if the time between exit and re-entry does not exceed  $110.4 - 3.8N$  ms.

|      | REM PRF3 MURA VARIABLE COL. + DIGIT ROUNDED FRACT. PRINT | MU   | PRF3 |
|------|----------------------------------------------------------|------|------|
| PRF3 | SXD COMMON,1 SAVE IR1                                    | PRF3 | 0001 |
|      | SXD COMMON+1,2 SAVE IR2                                  | PRF3 | 0002 |
|      | SXD COMMON+2,4 SAVE IR4                                  | PRF3 | 0003 |
|      | PXD 11,0 CLEAR AC                                        | PRF3 | 0004 |
|      | LDO 1,4 PARAMETER TO MQ                                  | PRF3 | 0005 |
|      | LGL 3 SHIFT N TO AC                                      | PRF3 | 0006 |
|      | STO COMMON+3                                             | PRF3 | 0007 |
|      | LGL 15 C, STARTING ADDRESS, TO AC                        | PRF3 | 0008 |
|      | ADD COMMON+3 C+N                                         | PRF3 | 0009 |
|      | STA PRF3+32 PLANT FRACTION CALL                          | PRF3 | 0010 |
|      | STA PRF3+42 ADDRESSES                                    | PRF3 | 0011 |
|      | PXD 4,0 CLEAR AC                                         | PRF3 | 0012 |
|      | LGL 3 (P-3) TO AC                                        | PRF3 | 0013 |
|      | ADD PRF3+131 (P-3) + 3                                   | PRF3 | 0014 |
|      | STO COMMON+4                                             | PRF3 | 0015 |
|      | RGL 15 B TO ADDRESS OF MQ                                | PRF3 | 0016 |
|      | LXA PRF3+3,1 SET IR1=11                                  | PRF3 | 0017 |
|      | CLA COMMON+3 N                                           | PRF3 | 0018 |
|      | ALS 2 4N                                                 | PRF3 | 0019 |
|      | STA PRF3+21 PLANT SHIFT ADDRESS                          | PRF3 | 0020 |
|      | CAL PRF3+126                                             | PRF3 | 0021 |
|      | ARS 0 SET UP NUMBER BANK                                 | PRF3 | 0022 |
|      | STO COMMON+22,1 FOR FIRST ENTRY                          | PRF3 | 0023 |
|      | TIX PRF3+22,1,1 LOOP RE-ENTRY, OUT AFTER 11 PASSES       | PRF3 | 0024 |
|      | PXD 6,0 CLEAR AC                                         | PRF3 | 0025 |
|      | DVP PRF3+123 DIVIDE BY 10                                | PRF3 | 0026 |
|      | ALS 28 POSITION REMAINDER                                | PRF3 | 0027 |
|      | ORS COMMON+22,1 FOR STORAGE                              | PRF3 | 0028 |
|      | TXI PRF3+29,1,1 ADD 1 TO IR1                             | PRF3 | 0029 |
|      | TXL PRF3+24,1,5 LOOP RE-ENTRY, OUT AFTER 5 PASSES        | PRF3 | 0030 |
|      | LXA COMMON+3,4 SET IR4=N                                 | PRF3 | 0031 |
|      | LXA PRF3+3,2 SET IR2=11                                  | PRF3 | 0032 |
|      | LDO 0,4 FRACTION IN MQ                                   | PRF3 | 0033 |
|      | MPY PRF3+123 MULTIPLY BY 10                              | PRF3 | 0034 |
|      | ALS 30,1 POSITION CODED DIGIT                            | PRF3 | 0035 |
|      | ORS COMMON+22,2 FOR STORAGE                              | PRF3 | 0036 |
|      | TIX PRF3+33,2,1 LOOP RE-ENTRY, OUT AFTER 11 PASSES       | PRF3 | 0037 |
|      | TXI PRF3+38,1,4 ADD 4 TO IR1                             | PRF3 | 0038 |
|      | TIX PRF3+31,4,1 LOOP RE-ENTRY, OUT AFTER N PASSES        | PRF3 | 0039 |
|      | MPR SELECT PRINTER                                       | PRF3 | 0040 |
|      | SPR 7 PULSE EXIT HUB 7 FOR F                             | PRF3 | 0041 |
|      | LXA COMMON+3,1 SET IR1=N                                 | PRF3 | 0042 |
|      | CLA 0,1 FRACTION IN AC                                   | PRF3 | 0043 |
|      | TPL PRF3+45 TRANSFER IF FRACTION IS +                    | PRF3 | 0044 |
|      | PSE 243,4 PULSE EXIT HUBS IF -                           | PRF3 | 0045 |
|      | TXI PRF3+46,4,-1 ADD -1 TO IR4                           | PRF3 | 0046 |
|      | TIX PRF3+42,1,1 LOOP RE-ENTRY, OUT AFTER N PASSES        | PRF3 | 0047 |
|      | LXA PRF3+11,1 SET IR1=4                                  | PRF3 | 0048 |
|      | CAL PRF3+131,1 SET UP CONSTANTS                          | PRF3 | 0049 |
|      | SLW COMMON+26,1 FOR FIRST USE                            | PRF3 | 0050 |
|      | TIX PRF3+48,1,1 LOOP RE-ENTRY, OUT AFTER 4 PASSES        | PRF3 | 0051 |
|      | CLA PRF3+132 HTR11                                       | PRF3 | 0052 |
|      | SUB COMMON+4 11-P                                        | PRF3 | 0053 |


|                  |                                      |           |
|------------------|--------------------------------------|-----------|
| STO COMMON+5     |                                      | PRF3 0054 |
| LXA COMMON+3,1   | SET IR1=N                            | PRF3 0055 |
| LXA COMMON+5,2   | SET IR2=11-P                         | PRF3 0056 |
| LXA COMMON+4,4   | SET IR4=P                            | PRF3 0057 |
| CAL COMMON+22,2  | (P+1)ST DIGIT                        | PRF3 0058 |
| ANA COMMON+22    | EXTRACT COLUMNS                      | PRF3 0059 |
| SUB COMMON+23    | DIGIT-5                              | PRF3 0060 |
| TMI PRF3+70      | TRANSFER IF DIGIT LESS THAN 5        | PRF3 0061 |
| TXI PRF3+62,2,1  | DIGIT=5 OR MORE, ADD 1 TO IR2        | PRF3 0062 |
| CAL COMMON+22,2  | P-TH DIGIT                           | PRF3 0063 |
| ANA COMMON+22    | EXTRACT COLUMNS                      | PRF3 0064 |
| CAS COMMON+24    | COMPARE WITH 9                       | PRF3 0065 |
| TRA PRF3+80      | AC MORE THAN 9                       | PRF3 0066 |
| TRA PRF3+115     | AC=9                                 | PRF3 0067 |
| CAL COMMON+22,2  | AC LESS THAN 9                       | PRF3 0068 |
| ADD COMMON+25    | CODED DIGIT + 1                      | PRF3 0069 |
| SLW COMMON+22,2  |                                      | PRF3 0070 |
| LXA PRF3+11,4    | SET IR4=4                            | PRF3 0071 |
| CAL COMMON+26,4  | SHIFT CONSTANTS, EXTRACTOR           | PRF3 0072 |
| ARS 4            | 4 PLACES TO RIGHT                    | PRF3 0073 |
| SLW COMMON+26,4  | FOR NEXT COLUMNS                     | PRF3 0074 |
| TIX PRF3+71,4,1  | LOOP RE-ENTRY, OUT AFTER 4 PASSES    | PRF3 0075 |
| TIX PRF3+55,1,1  | LOOP RE-ENTRY, OUT AFTER N PASSES    | PRF3 0076 |
| LXA COMMON+5,2   | SET IR2=11-P                         | PRF3 0077 |
| CAL PRF3+126     |                                      | PRF3 0078 |
| ORS COMMON+22,2  |                                      | PRF3 0079 |
| TIX PRF3+78,2,1  | LOOP RE-ENTRY, OUT AFTER 11-P PASSES | PRF3 0080 |
| CAL PRF3+124     | T IN AC                              | PRF3 0081 |
| ACL PRF3+125     | T-1                                  | PRF3 0082 |
| SLW COMMON+6     | STORE T (FIXED)                      | PRF3 0083 |
| SLW COMMON+7     | STORE T (SHIFTING)                   | PRF3 0084 |
| CAL PRF3+125     | EXTRACTOR IN AC                      | PRF3 0085 |
| SLW COMMON+8     |                                      | PRF3 0086 |
| LXA PRF3+24,1    | SET IR1=6                            | PRF3 0087 |
| LXA PRF3+5,2     | SET IR2=3                            | PRF3 0088 |
| LXA PRF3+18,4    | SET IR4=2                            | PRF3 0089 |
| CAL COMMON+9,4   | SHIFT T, EXTRACTOR                   | PRF3 0090 |
| ARS 4            | 4 PLACES TO RIGHT                    | PRF3 0091 |
| SLW COMMON+9,4   | FOR NEXT COLUMNS                     | PRF3 0092 |
| TIX PRF3+89,4,1  | LOOP RE-ENTRY, OUT AFTER 2 PASSES    | PRF3 0093 |
| LXA PRF3+3,4     | SET IR4=11                           | PRF3 0094 |
| CAL COMMON+22,4  | NUMBER IN AC                         | PRF3 0095 |
| ANA COMMON+8     | EXTRACT COLUMN                       | PRF3 0096 |
| CAS COMMON+7     | COMPARE WITH T                       | PRF3 0097 |
| TRA PRF3+99      | AC MORE THAN T                       | PRF3 0098 |
| CLA PRF3+99      | AC=T                                 | PRF3 0099 |
| LRS 1            | AC LESS THAN T                       | PRF3 0100 |
| TIX PRF3+94,4,1  | LOOP RE-ENTRY, OUT AFTER 11 PASSES   | PRF3 0101 |
| TNX PRF3+105,1,1 | LOOP RE-ENTRY, OUT AFTER 6 PASSES    | PRF3 0102 |
| TIX PRF3+88,2,1  | LOOP RE-ENTRY, OUT AFTER 3 PASSES    | PRF3 0103 |
| STQ COMMON+9     | STORE LEFT IMAGE                     | PRF3 0104 |
| TRA PRF3+87      |                                      | PRF3 0105 |
| STQ COMMON+10    | STORE RIGHT IMAGE                    | PRF3 0106 |
| CPY COMMON+9     | COPY LEFT IMAGE                      | PRF3 0107 |
| CPY COMMON+10    | COPY RIGHT IMAGE                     | PRF3 0108 |

CAL COMMON+6 T IN AC  
ANA PRF3+125 CLEAN IT OFF  
TNZ PRF3+81 TRANSFER IF NOT ZERO TO CONTINUE  
LXD COMMON+1 HERE IF=0, RESTORE IR1  
LXD COMMON+1,2 RESTORE IR2  
LXD COMMON+2,4 RESTORE IR4  
TRA 2,4 OUT  
CAL COMMON+22 HERE IF P-TH DIGIT IS 9  
COM  
ANS COMMON+22,2 0 REPLACES P-TH DIGIT  
TIX PRF3+61,4,1 TO TEST NEXT DIGIT  
CAL COMMON+24 HERE IF ALL DIGITS WERE NINES  
ORS COMMON+22,2 REPLACE WITH ALL NINES  
TIX PRF3+120,2,1 LOOP RE-ENTRY, OUT AFTER 11 PASSES  
TRA PRF3+70  
MTR 10 CONSTANT  
OCT 500000000000 EXTRACTOR  
OCT 740000000000 T  
OCT 001777777777 CONSTANTS  
OCT 001700000000  
OCT 000500000000  
OCT 001100000000  
OCT 000100000000  
MTR 9  
MTR 11

PRF3 0109  
PRF3 0110  
PRF3 0111  
PRF3 0112  
PRF3 0113  
PRF3 0114  
PRF3 0115  
PRF3 0116  
PRF3 0117  
PRF3 0118  
PRF3 0119  
PRF3 0120  
PRF3 0121  
PRF3 0122  
PRF3 0123  
PRF3 0124  
PRF3 0125  
PRF3 0126  
PRF3 0127  
PRF3 0128  
PRF3 0129  
PRF3 0130  
PRF3 0131  
PRF3 0132  
PRF3 0133

Page 1 of 2

MURA PRINTER BOARD



[illegible]